


welcome to oak presets

These instructions will help you to install oak presets on your mobile or on desktop. Hope you enjoy them.



Mobile only download

- . Download the FREE Adobe Lightroom Mobile app on your phone
- . Download the presets from your download link (you will receive this via email once you've purchased my presets).
- . Click 'Extract' to unzip the file, and when it's finished extracting:
- . Open the Lightroom Mobile app.
- . Click the Photo button in the bottom right corner.
- . Select and import all of the .DNG files from your downloads.
- . Select one of the .DNG files/photos.
- . Once selected, tap the 3 dots button in the top right corner of the screen and select 'Create Preset'.
- . Save the preset
 - Give the preset a name eg 'FALL into love'
 - Save it to a new group by clicking on the 'Preset Group' drop-down menu. Then click 'Create New Preset Group' and give the new group a name eg 'Oak Presets'.
 - Click this tick button in the top right corner to save the preset.

Lightroom CC install

- . Download your presets to your computer via the download link.
- . Unzip the presets file. For Mac users, simply double click on the file to unzip it.
- . Open Lightroom CC on Desktop
- . Select the Edit button on the right panel. Or simply press the 'E' key on your keyboard.
- . Click on 'Presets' - it's located at the bottom of the editing section.
- . Click on the three dots to the right of 'Presets' and then choose 'Import Presets'
- . Navigate to the 'oak presets' folder (most likely located in your downloads folder) and go to the 'Desktop_Files' folder
- . Select all the .xmp files within this folder and then click 'Import'
- . Your presets are now ready to use in the 'Presets' section. Click here for instructions on how to edit with my presets.

Lightroom Classic install

- . Download your presets to your computer via the download link.
- . Unzip the presets file. For Mac users, simply double click on the file to unzip it.
- . Open Lightroom Classic on Desktop
- . In the left panel, click on 'Presets'
- . Click on the '+' button to the left of 'Presets' and choose 'Import Presets'
- . Navigate to the 'oak presets' folder (most likely located in your downloads folder) and go to the 'Desktop_Files' folder
- . Select all the .xmp files within this folder and then click 'Import'
- . Your presets are now ready to use in the 'Presets' section. Click here for instructions on how to edit with my presets.

instagram: andreia.oak

WWW.ANDREIACARVALHO.PT

