

In this action convert your image to Modern Line Art Effect Action.

This action has been tested and works photoshop CS6, CC, CC 2015, CC 2015.5, CC 2017, CC 2018, CC 2019 + version.

INSTRUCTIONS

1. Your Photoshop document must be in RGB colour mode. To check this, go to the menu **Image -> Mode -> RGB Colour** check the right screenshot. Check in Figure 1.
2. Your Photoshop document must be setup in **8bits/Channel**. To check this, to the menu **Image -> Mode -> 8bits/Channel** check the right screenshot. Check in Figure 1.
3. **Press B** to select the Brush tool. On the top toolbar, make sure **Mode** is **Normal**, and both **Opacity** and **Flow** values are set to **100%**. Check in Figure 3
4. On the Layers panel, click on the menu icon on the top-right corner. Go to **Panel Options...**, and make sure that the **Use Default Masks on Fill Layers** and **Add "copy" to Copied Layers and Groups** are checked. Check in Figure 2
5. You are running the **English** version of Photoshop.
6. Avoid using small resolution images. For the best results, use Photos between **2000px - 5000px high/wide and 72-300 dpi resolution**.

If you have a lower resolution image, go to "Image" > "Image Size..." and change them to the specified dimensions. After the action has finished rendering, you can always reduce to your original size.




Figure 1




Figure 2



Figure 3

HOW TO USE ACTION:

1. Inside Photoshop, go to the **File > Open....**
2. Inside the Open window, navigate to the main Modern Line Art Effect Action folder which you downloaded.
3. Select the following files – “**Modern Line Art Effect Action**”, “**Modern Line Art Effect Pattern**” and “**Modern Line Art Effect Brush**”. Check in Figure 4
4. Click **Open** to load the files in **Photoshop**.




Figure 4




Figure 5

5. Open a photo to work with.
6. Leave the photo layer locked and set as the **Background**. In case it is not, go to **Layer > New > Background from Layer** to convert it into a Background locked layer
7. Create a new layer above the background layer called **brush**. Must be all in LOWERCASE. Check in Figure 5
8. With the **brush** layer selected, brush/trace the areas of your photo that you want to apply the effect to. Check in Figure 5
9. **Press B** to select the Brush tool. On the top toolbar, make sure **Mode** is **Normal**, and both **Opacity** and **Flow** values are set to **100%**.
10. Now **play** the action.

PLEASE, DON'T FORGET TO RATE THIS PRODUCT

Thanks...