

HOW TO USE THE ACTION

1. Make sure you are using the English version of Photoshop.

This actions have been created to using the English version of Photoshop so make sure your Photoshop is the English version. If not, don't worry.

You can change the language of version of your Photoshop.

(then you can return to your native language again with ease.)

Watch here: <https://youtu.be/f0q2QTZu2aw>

2. Use the RGB Mode and 8 Bits Color.

To check and set these settings, go to Image > Mode

and check the "RGB Color" and "8 Bits/Channel"

3. Make sure that the option "Add 'copy' to Copied Layers and Groups" is turned on.

This option applies only to CS5 and later versions of Photoshop.

On the "Layers" panel, click on the menu icon, go to "Panel Options...", and check that the "Add 'copy' to Copied Layers and Groups" is turned on.

4. Use a photo of size 2300-3500px for best results.

To check and set this setting, go to Image > Image Size

and check the size values.

5. Use a photo with 72dpi or higher.

To check and set this setting, go to Image > Image Size and check the Resolution value.

6. Set the Opacity of brush, the Flow of brush to 100%.

For to set the Opacity of brush and the Flow of brush, select Brush Tool, move the opacity and the flow sliders to 100%. Then Set the Brush Size to 500px and select Soft Round brush style.

7. Set your image as a background.

If your image have a difference name like as layer 0, select it and then go to Layer > New > Background from layer.

8. Create a new layer named “subject”.

Create a new layer named “subject” and paint your area.

9. Install the brush files.

Go to Edit > Presets > Preset Manager (or Edit > Preset Manager), select Brushes from the dropdown menu and then add the “AT_Watercolor_Brushes.abr” file using with the Load button.

10. Install the pattern file.

Go to Edit > Presets > Preset Manager (or Edit > Preset Manager), select Patterns from the dropdown menu and then add the “AT_Watercolor_Paper_Pattern.pat” file using with the Load button.

11. Install the action file.

Go to Window > Actions, the Action Panel will open.

Click on the menu icon, go to “Load Actions”.

Select your photoshop ATN file and click “Open”.

Your action file will load into the Actions panel.

(When the actions are loaded into the Actions panel, they will remain unless you delete the original folder where you saved the actions.)

If you want, you can also look these steps in youtube video:

<https://youtu.be/dSnpybsuDag>