

PRESET



BUNKER

Support
hello@presetbunker.com

Lightroom CC/Mobile (Paid)


Installation Instructions

Step 1:

Open Lightroom CC and press E to open the edit panel


Step 2:

At the bottom of the interface you will see a button labeled Presets, press this



Step 3:

Click the panel menu and select IMPORT PRESETS



Step 4:


Navigate to the folder you have unzipped all the files and choose the XMP.ZIP file

Step 5:


Expand the folder the Preset Bunker Folder with the name of the purchased preset

Step 6:

If you would like to adjust the strength of the preset, click on the "Browse Profiles" button in the edit panel



you can adjust the strength of the look of the profile



Syncing to Mobile

This will happen automatically but does require an active Creative Cloud subscription to work


Lightroom Classic (Paid) Installation Instructions

Step 1:

Open Lightroom Classic and press D to open the develop panel

Step 2:

Open the Presets panel on the left hand panel. Click on the + button then choose Import Presets.



Step 3:


Navigate to the folder you have unzipped all the files and choose the XMP.ZIP file

Step 4:

Expand the folder the Preset Bunker Folder with the name of the purchased preset

Step 5:

If you would like to adjust the strength of the preset, use the slider in the basic panel



Lightroom Mobile (Free)

Installation Instructions

1. Download and Unzip the DNG.zip file into your phone/tablet
2. Open Adobe Photoshop Lightroom CC Mobile
3. Click on Settings button (top right corner) and choose Add to button (bottom left corner)
4. Choose the location on your phone where you downloaded and unzipped the .dng files
5. Select and Import filters
6. Select Copy Settings
7. DNG file will install in Lightroom Mobile
8. Find and Open photos you want to edit in LR Library
9. Click on Settings (top right corner)
10. Copy Settings, then click on Select all and unselect Crop setting and click on OK button
11. Choose a photograph you would like to edit Lightroom
12. Again click on Settings button (top right corner)
13. Then Click on the Select Paste Settings
14. If the preset includes a profile (most do) you can change the strength of the preset using amount slider in the profile tab (see Lightroom Mobile instructions)



15. Enjoy applied presets

Frequently Asked Questions & Common Issues

My photo doesn't look like your examples what is wrong?

There are a couple of reasons that could be causing problems I will list the common reasons below

1. The presets have been tested on a wide range of JPEG & RAW photos but all photos are different, you have different lighting, colours and tones in every photo so the presets will affect them differently and as a general rule the presets cannot make any major colour changes, for example a photo with a plain white background will not get a pink background from a preset.
2. Check your white balance, this is a common problem that the photo White Balance (WB) is off if you are unsure what it should be Lightroom offers the option of AUTO WB this usually gets the colours looking pretty good.
3. Exposure is wrong, although the presets do sometimes adjust the exposure this isn't an automatic adjustment and is a set number so it could end up over or under exposing your photo incorrectly. This is a simple fix if it is too bright reduce the exposure if it is too dark increase the exposure but remember to do the adjustments in small increments.
4. The preset may not affect the colours or highlights / shadows in your photos so presets designed to work with autumn colours and make them pop for example will not look as good with an grey urban photo.
5. Treat all presets as a good jumping off point, while there is a very good chance your photo will look great with just one click it is also likely there may need to be some further adjustment. Maybe the photo is too bright so follow the hints for exposure above. Maybe the saturation is too much then you will need to reduce this to make the photo look good or the opposite and increase it to make it pop more.
6. I saved the preset in the free version and the profile disappeared what happened? This is either a feature or bug of Lightroom, you can copy and paste the preset with the profile but not save it using the free version you will need to keep the included DNG files in your library or subscribe to use the XMP files which will let you quickly choose the profile using the profile selector.